

AerDocsis System Software Software Release Notes

lomoM8 20.2.7659

February 2nd, 2026

Contents

1. Compatible devices and minimum versions.....	3
2. What's new in this release?.....	4
2.1 Fixed Issues.....	4
2.1.1 Common to all devices.....	4
2.1.2 BS450.....	4
3. Important notes.....	5
3.1 IMPORTANT NOTE: Radio FW update.....	5

1. Compatible devices and minimum versions

Product family	Devices	Minimum versions
Base Stations		
BS400 and BS800	AXS-BS-450-N AXS-BS-452-N AXS-BS-850-N	HoneybeeM1 19.6.6172

2. What's new in this release?

2.1 Fixed Issues

2.1.1 *Common to all devices*

Spectrum Analysis

An issue that caused spectrum analysis to take longer than expected in single-cycle mode has been fixed. This reduces the time the system is interrupted.

Additionally, another bug has been fixed, this bug caused radios not to power on automatically after spectrum analysis in continuous mode when they were previously running.

REST API

A problem affecting the `/gui/local_aa.cgi/aa_file` resource of the REST API has been fixed. When attempting to upload a provisioning file, the server returned an error despite having updated it correctly. It now returns the HTTP 200 OK response code.

2.1.2 *BS450*


Radio Startup

A bug that caused radios to lose files required for startup has been fixed. This caused a permanent loss of communication with the radios (updating to this firmware will restore communication).

3. Important notes

3.1 IMPORTANT NOTE: Radio FW update.

After updating to this release and restarting the device, the system will check if it needs to make updates to the radios' firmware, so it may take longer than usual to be fully operational. If these updates are necessary, the system will notify you on the website with a message as shown in the following image:



It is important that the equipment is not turned off electrically until the update is completed. Otherwise, the firmware may be corrupted and it will be necessary to send the device to the factory for manual updating.

The devices that may require this additional update step are the following:

Model	Serial number
AXS-BS-850-N	A24XXX, A22X1X
AXS-BS-452-N	A25XXX, A23X04, A23X05
AXS-BS-450-N	All